






# GRAVOGRAPH NEW HERMES


## Measuring Tools


1. Measuring Tools supplied with the Graphic Level of Gravostyle facilitate accurate measurement of objects on the screen.



- Click on the Distance Measurement Tool . You will notice that the cursor has changed. Click to set the start point of the measurement, drag to the end point. The measurement is displayed in the lower left corner of the Main Edit page. Press the space bar to drop the measure tool.



3. Click the Size Measurement Tool icon . Click in one corner of the object to be measured, and drag diagonal to the opposite corner. At the bottom left corner will be displayed the height, width and diagonal measurements. Press the space bar to drop the tool.



- Click the Angle Measurement Tool icon . Click on a start point of an angle, drag to a second point on the angle. The angle in degrees can be read in box in the lower left corner of the screen. Press the space bar to drop the tool.

